




General Information: We recommend using IMAP instead of POP for your Incoming Server type. Your Outgoing Server may be either SSL or TLS depending on your Email program capabilities.

<p style="text-align: center;"><u>someone@ccrtc.com</u></p> <p>Incoming Mail Server: mail.ccrtc.com Port: 993 (IMAP) Port: 995 (POP) Requires SSL: Yes</p> <p>Outgoing Mail Server: smtp.ccrtc.com Port: 465 (SSL) Port: 587 (TLS) Requires Authentication: Yes Use same settings as incoming mail server</p> <p>Full Name: Your Real Name User Name: Your full Email address Email Address: Your full Email address Password: Your Email password</p>	<p style="text-align: center;"><u>someone@iendeavor.com</u></p> <p>Incoming Mail Server: mail.iendeavor.com Port: 993 (IMAP) Port: 995 (POP) Requires SSL: Yes</p> <p>Outgoing Mail Server: smtp.iendeavor.com Port: 465 (SSL) Port: 587 (TLS) Requires Authentication: Yes Use same settings as incoming mail server</p> <p>Full Name: Your Real Name User Name: Your full Email address Email Address: Your full Email address Password: Your Email password</p>
---	---

Email Setup for: **Windows Live Mail**

To add an Email account go to accounts.
Then select the add email icon.



Fill in the forms with your information and other details as exemplified below then select Next.



Add your email accounts

If you have a Windows Live ID, sign in now. If not, you can create one later.

[Sign in to Windows Live](#)

Email address:

[Get a Windows Live email address](#)

Password:

Remember this password

Display name for your sent messages:

Manually configure server settings

Most email accounts work with Windows Live Mail including

Hotmail
Gmail
and many others.

Cancel

Next

Windows Live Mail

Configure server settings

If you don't know your email server settings, contact your ISP or network administrator.

Incoming server information

Server type: IMAP

Server address: mail.example.com Port: 993

Requires a secure connection (SSL)

Authenticate using: Clear text

Logon user name: someone@example.com

Outgoing server information

Server address: smtp.example.com Port: 465


Requires a secure connection (SSL)

Requires authentication

Cancel Back Next

Your Email setup is now complete!

If you need to verify your settings, go to accounts and select properties.



Properties

General Servers Security Advanced IMAP

Mail Account

Type the name by which you would like to refer to these servers. For example: "Work" or "Windows Live Hotmail".

Example (someone)

User Information

Name: John Doe

Organization:

E-mail address: someone@example.com

Reply address:

Include this account when receiving mail or synchronizing

OK Cancel Apply

Properties

General Servers Security Advanced IMAP

Server Information

My incoming mail server is a IMAP server.

Incoming mail (IMAP): mail.example.com

Outgoing mail (SMTP): smtp.example.com

Incoming Mail Server

Email username: someone@example.com

Password: ●●●●●●

Remember password

Log on using clear text authentication

Log on using secure password authentication

Outgoing Mail Server

My server requires authentication Settings...

OK Cancel Apply

Outgoing Mail Server [X]

Logon Information

Use same settings as my incoming mail server

Log on using

Account name:

Password:

Remember password

Log on using Secure Password Authentication

OK Cancel

Properties [X]

General Servers Security Advanced IMAP

Signing certificate

Select the signing certificate below. This will determine the digital ID used when signing messages with this account.

Certificate: Select...

Encrypting preferences

Select the encryption certificate and algorithm. These are included with your digitally signed messages so others can send encrypted mail to you with these settings.

Certificate: Select...

Algorithm: 3DES ▾

OK Cancel Apply

